Starting from scratch: Code cards

```
Card One

when clicked
pen down
set pen color to
repeat 3
move 250 steps
wait 1 secs
turn (* 120 degrees
wait 1 secs
```

```
Card Two

when clicked

pen down

set pen color to

repeat 5

move 150 steps

wait 1 secs

turn (* 72 degrees

wait 1 secs

**
```

```
when clicked

point in direction 25v

pen down

set pen color to

set pen size to 3

repeat 300

move 2 steps

turn 1 degrees

repeat 240

move 1.15 steps

turn 1 degrees

***
```

```
when clicked

point in direction 27

pen down

set pen color to

repeat 240

move 1 steps

turn 1 degrees

****
```

Starting from scratch: Code cards

```
Card Five
       when 🖊 clicked
      point in direction 45°
      set pen color to
      set pen size to 5
      move 200 steps
      wait 1 secs
turn (180 degrees
        rait 1 secs
      move 100 steps
       wait 1 secs
      turn ( 90 degrees
      move 100 steps
        rait 1 secs
      turn (180 degrees
      move 200 steps
      wait 1 secs
turn (4 180 degrees
                                                      **
```

```
define hexagon
repeat 6
wait 1 secs
move 50 steps
wait 1 secs
turn (* 60 degrees
wait 1 secs
when clicked
point in direction 90
pen down
set pen color to
repeat 3
turn (* 120 degrees
hexagon
****
```

```
Card Seven

define 4 gon
repeat 4
nove 150 steps
wait 1 secs
turn ( 90 degrees
wait 1 secs
turn ( 120 degrees
wait 1 secs
turn ( 120 degrees
wait 1 secs

when clicked
point in direction 90
pen down
set pen color to
4 gon
3 gon
****
```

```
when clicked
if on edge, bounce
point in direction O'
go to x: O y: O
pen down
set pen color to
set angle to O
forever
set pen size to pick random 1 to 5000
set angle to pick random 1 to 10
set angle to pick random 1 to 359
turn angle degrees
move pick random 1 to 100 steps
```

Starting from scratch: Code cards

```
Card Nine

define round
repeat 360
move 2 steps
turn (1 degrees

when clicked
pen down
set pen color to
round

*
```

```
Card Ten
                        when / clicked
  define 3/4 c
                        point in direction 07
     at 270
                        pen down
   move 1 steps
                        set pen color to
                        set pen size to 3
   turn ( 1 degrees
                        3/4 c
                        turn 🔊 90 degrees
                        move 100 steps
                        pen up
                        move 30 steps
                        pen down
                        change pen size by 10
                        move 5 steps
                        pen up
                        move 20 steps
                                         ***
```

```
Card Eleven
                          when P clicked
 define Clockwise
                          point in direction 0
 repeat 360
                          go to x: 0 y: 0
   move 1 steps
                          pen down
   turn (1 degrees
                          set pen color to
                          set pen size to 10
                          repeat (5)
  define anti clockwise
                            change pen color by 50
  repeat (360)
                            Clockwise
   move 1 steps
                            change pen color by 50
   turn 🖹 🚺 degrees
                            anti clockwise
                                               ***
```

```
Card Twelve
                      define four
                      set Step to pick random 20 to 100
                      repeat 4
 when / clicked
                        move Step steps
 set pen color to
                        turn () 90 degrees
 set pen size to 3
                        wait 1 secs
 go to x: 0 y: 0
  repeat 100
   change pen color by pick random 1 to 50
   go to x: pick random -80 to 80 y: pick random -80 to 80
   pen down
   point in direction 90*
   four
   pen up
                                                   ****
```